

Chapter 9

Nursery and field establishment

K.I. Punnoose and Radha Lakshmanan

1. Introduction
2. Nursery establishment
 - 2.1 Ground nursery
 - 2.1.1 Selection of site
 - 2.1.2 Preparation of land and nursery beds
 - 2.1.3 Seed germination beds
 - 2.1.4 Planting in nursery
 - 2.1.5 Nursery for seedlings and budded stumps
 - 2.1.6 Budwood nursery
 - 2.1.7 Nursery for stumped buddings
 - 2.2 Polybag nursery
3. Field planting
 - 3.1 Preparation of land
 - 3.1.1 Clearing
 - 3.1.2 Roads, fences and buildings
 - 3.1.3 Planting density
 - 3.2 Lining
 - 3.2.1 Rectangular or square planting
 - 3.2.2 Quincunx or equilateral - triangle planting
 - 3.2.3 Contour planting
 - 3.3 Pitting and refilling
 - 3.4 Soil conservation
 - 3.5 Drainage
 - 3.6 Materials for planting
 - 3.6.1 Seeds and seedling stumps
 - 3.6.2 Budded stumps
 - 3.6.3 Advanced planting materials
 - 3.6.4 Seedlings vs. clones
 - 3.7 Planting
 - 3.7.1 Seed at stake
 - 3.7.2 Seedling and budded stumps
 - 3.7.3 Stumped buddings
 - 3.7.4 Polybag plants

References

1. INTRODUCTION

Nurseries are established and maintained for raising various materials for planting. These include seedling stumps, budded stumps and advanced planting materials like polybag plants, stumped buddings and soil core plants. Mother plants or source bushes for the

multiplication of budwood are also grown in nurseries. The practice of raising plants is easier and cheaper in nurseries than in the main field. Moreover, nurseries offer an opportunity for selection of vigorous and uniform plants. The requirement of area under different types of nurseries for raising materials for planting 100 ha plantation is given in Table 1.

Table 1. Requirement of area for various types of nurseries for producing planting materials necessary for 100 ha

Planting material to be produced	Spacing (cm)	Density (per ha)		No. of plants* required for 1 ha of main field	Area required (ha)	
		Initial	Final		Effective	Gross**
Budded stumps	30 x 30	111110	74074	500	0.675	0.750
Seedling stumps	30 x 30	111110	88000	550	0.625	0.695
Stumped buddings, Maxi	90 x 90	12350	9880	500	5.000	5.550
Stumped buddings, Mini	60 x 60	27775	22220	500	2.000	2.500
Polybag 2 - 3 whorls	-	-	25000	500	2.000	2.500
Polybag 6 - 7 whorls	-	-	18000	500	2.750	3.400

* Includes the number of plants required for vacancy filling during the first year

** Includes additional space required for footpaths, drains, etc.

2. NURSERY ESTABLISHMENT

Planting materials for establishing rubber plantations are generated in ground and polybag nurseries.

2.1 Ground nursery

Ground nurseries are established for the production of budded stumps, stumped buddings and budwood.

2.1.1 Selection of site

The site selected for a ground nursery should have good accessibility for supervision and transport of materials. If the purpose of the nursery is to raise materials for planting a large area in the estate, it may preferably be located at a suitable site within this area itself. A good soil depth of at least 75 cm is essential. Loamy soils are ideal for ground nurseries. Extremely sandy soils are not suitable since leaching of plant nutrients is faster. Retention of moisture is poor in such soils, necessitating frequent watering during summer months. Soils containing too much of clay are also unsuitable mainly because of poor drainage. A well-drained, level area is ideal for a nursery since the various operations will be easy and cheap in such sites. However, undulating lands are also suitable if adequate soil conservation measures are adopted. Contour terracing is done where the slope is in excess of two per cent. Waterlogged areas should be avoided. Water table should be sufficiently low to allow sufficient depth in the soil for root development. Shade free areas are preferred. Land with a history of intensive cropping needs proper build up of the nutrient status to the satisfactory level.

2.1.2 Preparation of land and nursery beds

For the preparation of a ground nursery, the soil is first dug to a depth of 60 to 75 cm. Stones, stumps, roots, *etc.* present in the soil are removed and the soil is brought to a fine tilth. Beds should be 90 to 120 cm wide and of convenient length. In level lands, raised beds are made with footpaths of about 45 cm width between the beds, and in undulating lands beds are prepared along the contours, one below the other. At the time of preparation of nursery beds, 25 kg of compost or well-rotten cattle manure and 3.5 kg of powdered rock phosphate (20 - 24% P_2O_5) are incorporated for every 100 m² of nursery bed (Rubber Board, 1999). When nurseries are established in newly cleared forest areas rich in organic matter, compost or cattle manure need not be applied during the first year. Similarly when the same area is repeatedly used as a nursery, rock phosphate need be applied only once in three years. Drainage and pathways should be provided appropriately.

2.1.3 Seed germination beds

Rubber seeds are first germinated in germination beds and then planted in nursery. A well-drained area with moderate shade is the ideal site for germination beds. Level beds of 90 cm width and convenient length are prepared with walking space in between. The beds should be raised 10 to 15 cm above the soil surface to avoid waterlogging. A free draining friable material, like river sand, spread above the bed to a thickness of 5 cm is used as the medium for germination. Rubber seeds are viable only for a short period and are put in germination beds as soon as obtained. Seeds are washed thoroughly (Plate 13. a) to remove charcoal and other packing debris and spread over the bed in a single layer touching one another and pressed gently into the sand (Dijkman, 1951). In order to prevent loss of too much moisture from the rooting medium, the beds are covered with a thin layer of gunny bag, coir matting or similar material (Plate 13. b). A high level of moisture is maintained in the bed by evenly sprinkling water early in the mornings and late in the evenings (Plate 13. c). Germination of the seeds starts within six to seven days after sowing (Plate 13. d). The beds should be inspected daily and the germinated seeds picked up and collected in a bucket containing water as soon as the radicle emerges for planting in the nursery beds or main field (Plate 13. e,f). If the picking of germinated seeds is delayed, chances of damage during handling will be greater. Seeds which do not germinate within two to three weeks should be discarded as they are likely to give rise to weak seedlings (Edgar, 1958).

2.1.4 Planting in nursery

For planting germinated seeds in the nursery beds, small holes enough to accommodate the seeds in a horizontal position and approximately 5 cm deep are made. The seeds are carefully placed in the holes with the radicle pointing downwards and covered with soil. The sprouted seeds should be planted when the young root is less than 2 cm long (Plate 13. g). The germinated seeds should be carefully handled, to prevent damage of the radicle. Spacing varies according to the type of planting material to be raised in the nursery. The common spacing adopted for raising seedling stumps is 30 x 30 cm. To produce green-budded stumps 23 x 23 cm spacing may be followed. For brown-budded

stumps a spacing of 30 x 30 cm or staggered pairs of rows 60 cm apart and 23 cm between plants may be adopted (Edgar, 1958). A spacing of 60 x 60 cm, 90 x 30 cm, 90 x 60 cm or 90 x 90 cm is required to produce various kinds of stumped buddings. For raising soil core plants, a spacing of 35 x 35 cm, 38 x 30 cm or 60 x 60 cm may be followed (RRIM, 1976a). The spacing adopted for budwood nursery is 90 x 60 cm or 120 x 60 cm., wider spacing being between rows.

The rows are first marked on either end of each nursery bed using row markers. A long cord of coir rope, wire or country twine, with the planting distance along the row marked on it, is stretched tight along the length of the bed on the row markers on either end and germinated seeds are planted at each mark along the line (Plate 13. h). In budwood nursery, budded stumps are planted at the required spacing. Alternatively, seeds can be directly sown in the beds at the required spacing and budded *in situ*. After budtake they are cut back and the scion allowed to develop.

2.1.5 Nursery for seedlings and budded stumps

For rapid and economic production of good quality planting materials, very careful management of the nursery is necessary. In India, seed fall is generally from July to September and hence the period available for nursery growth is about 10 months. Therefore, efficient nursery management should aim at production of the maximum number of buddable or transplantable seedlings at the end of the 10 month period (Plate 14. a-c). Unhealthy and weak seedlings should be removed. The ideal time for this culling is three to four weeks after the first fertilizer application, by which time the vigorously growing and stunted plants can easily be distinguished (Abdulkalam and Punnoose, 1975).

The nursery beds should always be kept free of weeds. Generally three rounds of weeding are needed. In India, hand weeding is commonly practised (Plate 14. d). The first weeding is done just before application of the first dose of fertilizers and the second weeding before the second dose. The third round of weeding is done just before commencement of budding during May or June. The first round of manual weeding can be replaced with the application of pre-emergence herbicides (Mathew and Punnoose, 1975; Lakshmanan *et al.*, 1995a). After the final preparation of the nursery beds, diuron at the rate of 2 kg per ha in 700 L water is sprayed on the beds and germinated seeds planted five days later. However, planting germinated seeds on the same day of herbicide application does not result in any harmful effect (Lakshmanan and Punnoose, 1999) that there is only minimum disturbance to soil while planting the seeds. The beds can be kept free of weeds till the first round of fertilizer application (6 - 8 weeks) by adopting this method.

Mulching is an important operation to be followed in seedling nurseries before the beginning of the summer season and after the second round of fertilizer application. Natural materials such as tree loppings, dry leaves, undergrowth from forests, grass cuttings and cut cover crop material are commonly used after they are dried (Plate 14. e). Field trials indicate that 'African payal' (*Salvinia* sp.), a noxious weed found in the waterways, could also be used as mulch material in nurseries. Mulching is very effective in retaining soil moisture in the nursery beds during summer months. Apart from conserving soil

moisture, it also lowers soil temperature, checks weed growth and adds organic matter to the soil in nurseries (Potty *et al.*, 1968; Lakshmanan *et al.*, 1995b). The mean percentage of available soil moisture measured at 15 cm depth in April was 88.6 in the mulched beds. The unmulched beds retained only 32.8 per cent available moisture which was insufficient for the proper growth of the plants (Abdulkalam and Punnoose, 1975). A single round of good mulching in December is adequate (Potty *et al.*, 1968). Black polythene sheets (Plate 14. f), properly anchored to the soil to prevent them from being blown away by wind, can also be used for mulching (Yeoh *et al.*, 1987; Lakshmanan *et al.*, 1995b). Spreading a thin layer of soil above the sheet is an effective way to achieve this.

Experiments conducted in five different regions to study the effect of nitrogen, phosphorus, potassium and magnesium on Tjir 1 seedlings in nurseries showed that the optimum fertilizer requirements could be fixed at 500, 250 and 100 kg per ha of N, P_2O_5 and K_2O respectively (Abdulkalam and Punnoose, 1975). Application of magnesium at the rate of 37.5 kg per ha was also found beneficial in places where the soil was deficient in magnesium. Field experiments indicate that ammonium sulphate, urea and ammonium sulphate nitrate were equally efficient in improving the growth of seedlings, but considering the unit costs, urea is the cheapest source of nitrogen (Punnoose *et al.*, 1976). Different sources of phosphatic fertilizers like rock phosphate, super phosphate, ammonium phosphate sulphate, basic slag and bonemeal had similar responses. However, based on unit cost and long residual effect, rock phosphate is recommended for nurseries. Lack of response of nursery seedlings to micronutrients has been reported (Potty *et al.*, 1976). Manuring may preferably be carried out after ascertaining the specific requirements of individual nurseries by soil analysis. If this is found difficult, the general fertilizer recommendation may be followed.

During the dry period which usually extends from December to April, the nurseries should be irrigated. In areas where distinct dry season is experienced, growth will not be satisfactory without watering (Webster, 1989). In a seedling nursery, when summer irrigation was given to supply 25 per cent of the estimated soil moisture deficit for a period of six months, there was an increase in dry matter production by 17 per cent over unirrigated control plants (Haridas, 1980). Field experiments have indicated that the efficiency of applied fertilizers increases with summer irrigation (Pushparajah and Haridas, 1977). In large nurseries, overhead sprinkler irrigation systems are ideal (Plate 14. g). Manual watering is convenient and cheap for small nurseries. The nursery beds should be mulched before commencement of irrigation. The quantity of water required varies with soil, climate and age of the plants. Daily watering is preferred during the initial weeks. Later, the frequency of irrigation can be reduced to once in two or three days. When the seedlings are sufficiently grown they are used for budding or directly used as seedling stumps.

2.1.6 Budwood nursery

Buds required for budgrafting are collected from budwood, obtained from plants raised specifically for this purpose. Budwood nurseries are of two types, namely brown budwood nursery (Plate 15. a) and green budwood (bud shoot) nursery (Plate 15. c). The former produces brown buds while the latter, green buds.

Site selected for establishing the budwood nursery is first cleaned and levelled. Terracing is done on slopes. Soil is first dug to a depth of 45 to 60 cm. Planting can be done with polybag plants, budded stumps or seed at stake followed by *in situ* budding. Spacing usually adopted for brown budwood nursery is 90 x 60 cm. For green bud shoot nursery the spacing is 1 x 1 m or 90 x 90 cm. Proper fertilizer application may be carried out to ensure good growth. Other agronomic practices such as irrigation, mulching, weeding, shading, protection against diseases and pests are followed in a similar manner as for seedling nursery. During the first year of planting only one shoot is allowed to grow. About 1 m of brown budwood can be obtained from this after one year. From the second year, two or three shoots are allowed to develop on a plant depending on the spacing adopted. To remove the leaves present in the brown-coloured budwood, the leaflets are first removed by clipping the tip of the leaf stalk. After about one week the leaf stalk dries and falls off. Budwood is then harvested by sawing off, leaving about 15 cm at the base (Plate 15. b). From this portion shoots develop in the subsequent season. Green bud shoot plants are shaped from brown budwood plants. For this, a well-established brown budwood plant is first cut back at a height of about 75 cm. A number of shoots emerge below the cut end. Among these, three to five most vigorous ones alone are retained and the rest removed. When these shoots have grown and produced brown wood to a length of about 5 cm they are pruned at the point where the brown colour ends so as to produce more branches. Two to three most vigorous branches are retained on each shoot and the others cut off. When these secondary branches develop brown colour at the basal 5 cm they are again pruned. New branches arise from these and give the budwood plant a bushy appearance. For producing green shoots, all the branches of a green bud shoot plant (also called source bush) are pruned. The new branches arising are harvested (Plate 15. d) when one whorl of leaves develops (Tinley, 1962; RRIM, 1964; RRIM, 1976b). The harvested budwood (Plate 15. e) is cut into pieces of convenient length before being taken to the nursery beds for budding.

2.1.7 Nursery for stumped buddings

The establishment and maintenance of nurseries for raising stumped buddings are similar to that of budwood nurseries. However, green budding at four to five months age is recommended for stumped buddings. Every cultural operation should be done in such an intense manner that the plants grow at a fast rate. Mulching and irrigation during dry weather should be practised efficiently. Regular manuring with NPKMg 10:10:4:1.5 mixture is to be done once in two months starting from one month after cutting back. Manuring can be started with 25 g per plant which may gradually be increased to 50 g for every application. Frequent rounds of weeding and prophylactic spraying against shoot rot and leaf spot diseases and pests are to be strictly followed to facilitate healthy growth of the plants.

Stumped buddings can be prepared either as maxi stumps or mini stumps. For the production of maxi stumps, plants are grown in the nursery until the scions develop brown colour to a height of 2.4 m. This takes about 18 months after cutting back. In order to produce mini stumps, the scion should produce brown bark up to 60 cm from bud union, which requires about five to six months after cutting back. The planting of

maxi or mini stumps should be done when rains are continuously received. The percentage of establishment has been found to be poor in the case of stumped buddings. Since the introduction of polybag plants, the use of stumped budding is no longer popular. Core stumps and soil core plants are other planting materials that are not popular now.

2.2 Polybag nursery

Planting materials in polybags can be prepared by two different methods. Budded stumps can be planted in polybag and the scion allowed to develop till they are ready for planting in the field. In the other method, germinated seeds are planted in polybags and bud-grafted when five to six-month-old. The former gives greater opportunity for selection of the most vigorous plants and avoids wastage of bags containing poor seedlings and budding failures. The roots of budded stumps can be treated with indolebutyric acid (IBA), a hormone which enhances root growth (Pakianathan *et al.*, 1978). Dipping root in cow dung slurry before planting enhances root development.

The bags may be of black or transparent polyethylene. Transparent bags, when used, should always be kept buried in soil, as otherwise, the development of roots will be affected. The use of black polyethylene bags is generally preferred. Depending on the size of the plant to be produced, bags of different dimensions may be used. Polythene bags of lay flat dimension 55 to 60 cm length and 25 to 30 cm width which can hold about 8 to 10 kg soil, are usually used for raising plants up to two to three whorl stage. For producing plants of six to seven whorls, larger bags of 65 x 35 cm size and holding about 23 kg soil should be used (RRIM, 1973). In order to facilitate drainage, sufficient number of holes should be punched on the lower half of the bags. Low density polyethylene (LDPE) sheet of 400 gauge and 500 gauge thickness are usually used for making small bags and large bags respectively. Bags made of high density polyethylene (HDPE) sheets can also be used for this purpose. However, such bags are likely to deteriorate when exposed to sunlight for long periods.

The soil used for filling the bags should have good moisture and nutrient retention capacity, promote root development and bind the roots firmly to prevent damage during transport (Taryo - Adewiganda and Hasanudin, 1995). Soils with clay-loam texture, good structure and friability are ideal for this purpose (Marattukalam and Saraswathyamma, 1992). The fertile topsoil collected after removing the surface vegetation and leaf litter is ideal for filling the bags (Plate 16. a). Before filling, large clods of soil are broken, and if too wet, partially dried. The soil is cleaned by removing stones, roots and stubbles. While filling, the bag should be gently tapped to ensure compact filling of soil without leaving air spaces. The bag is filled up to about 2 cm below the brim (Plate 16. b). Powdered rock phosphate at the rate of 25 g for small bags and 75 g for large bags is mixed with the top layer of soil. The filled bags can be kept in the nursery either in trenches (Plate 16. c,d) or on the ground supported with wooden poles (Marattukalam and Saraswathyamma, 1992). The former method is better as it would give greater protection of the bags and better growth of the plants. Trenches having width equal to the diameter of the bag are usually dug in pairs. For small bags, depth of trench may be about 20 cm and the distance between rows in a pair of trenches 15 cm. The corresponding

depth and distance for large bags are 30 cm and 20 cm . The gap between bags of same trench is 10 cm (Marattukalam, 1981). Footpath of 75 cm width may be left between two pairs of trenches. After placing the bag in the trench, the excavated soil is filled in the gap between them. The remaining soil is mounted around the bags. Planting of budded stumps or sprouted seeds is undertaken thereafter. When budded stumps are used, the bud patch should face the footpaths to facilitate growth of sprouts. Regular cultural operations like manuring, watering, weeding, shading and plant protection are adopted. Application of NPK Mg 10:10:4:1.5 mixture is done at monthly intervals. During the first month 10 g of the mixture is given per bag which is gradually increased to 30 g in four months time (Rubber Board, 1999). Fertilizer application should be avoided when the leaves are very tender. While applying fertilizer, care should be taken to prevent it from coming in contact with the young plant as it may cause scorching. Watering should be done soon after manuring. During dry periods, irrigation should be done regularly (Zehari-Husny and Aidi-Daslin, 1995). Watering can be done manually in small nurseries while sprinklers or drip irrigation system is more economical in large nurseries. Too much watering should be avoided to prevent waterlogging. During summer months, partial shade may be provided to the plants by erecting overhead shade (Plate 16. e,f). Appropriate prophylactic and curative measures may be taken against diseases and pests.

Polybag plants are advanced planting materials which contribute to reduction in immaturity period. Bagged plants should be transplanted to the field, with minimum disturbance to the root system for proper establishment (Marattukalam and Nair, 1982; Marattukalam and Saraswathyamma, 1992). Such plants also help to achieve a uniform stand and are also useful for vacancy filling and late planting. Because of these advantages the use of polybag plants has become very popular.

3. FIELD PLANTING

In India, the area available for planting rubber can be categorized into forest clearings, cropped lands (where other crops were grown) and rubber replantings.

Considerable portion of the existing rubber plantations was established in forest clearings. However, in future, the availability of such areas is limited. There is a growing tendency for converting other cropped lands to rubber. The incidence of the root wilt disease of coconut in the central region of Kerala has resulted in the conversion of some coconut gardens to rubber plantations. Areas under less profitable crops like cashew and cassava are also being planted with rubber in South India. Areas once under rubber are generally being replanted with rubber.

3.1 Preparation of land

This includes various operations such as land clearing and construction of roads and buildings.

3.1.1 Clearing

The nature and extent of clearing required will depend on the previous land use. The land should be cleared off the existing vegetation. These operations will be more elaborate and tedious when planting is planned in forest clearings compared to other crop

lands and rubber replantings. Since June-July is the best season for planting in India, all the pre-planting operations should be completed well in advance. The clearing operations for jungle lands are more elaborate and therefore should be started sufficiently early to avoid delay in planting. Large trees of good timber value are removed first, followed by removal of smaller ones. Lastly the undergrowth is slashed and left in the field for about one month for drying. Appropriate herbicides also can be used to kill the weeds and undergrowth. Uprooting of stumps of trees may be avoided, if expensive. However, large stumps which interfere with planting lines in terraces have to be removed. A light burn may be given after the slashed material is sufficiently dried. Most of the woody material including small branches are recovered for firewood before burning. Light burning reduces the bulk of the stubble and trash left in the field and helps to have closer supervision of the field operations. This would slow down the regeneration of weeds and help establishment of cover crops. However, excessive burning is harmful as it will destroy humus and adversely affect the structure and fertility of the soil.

When rubber is planted on a land where other tree crops are grown, land preparation is similar to that of forest clearings. In replanting areas, the old rubber trees are cut as close to the ground as possible and the timber removed. The stumps of trees may be left in the field and allowed to rot. The twigs and leaves of trees along with the existing weeds may be burnt or collected and stacked along the contour. Lining and digging of pits before felling of the trees is also practised in some plantations. Although cutting terraces before felling may help in saving time, the terraces may be damaged when the trees are felled and removed. Poisoning of trees using sodium arsenate or 2,4,5-T, though followed in some countries, is not practised in India.

3.1.2 Roads, fences and buildings

A network of well-laid out roads and footpaths is necessary for easy transportation of inputs to various fields and latex to the processing factory and also for efficient supervision of field operations. It is estimated that a minimum length of 25 km road may be required for a plantation of 1000 ha. The position of roads may be traced before the commencement of lining for rubber, so that sufficient strips of land could be reserved for roads.

Adequate provision should be made for estate office, stores, processing factories, residential accommodation, etc. The requirement of buildings varies depending on the size of the plantation and the type of processing of the produce. The sites of these buildings may be suitably located and reserved. The plantation should be protected all around by erecting fences or walls to keep away grazing cattle and to prevent pilferage. Barbed wire fences with five or six strands fixed on wooden, stone or concrete posts are commonly used.

3.1.3 Planting density

It is important to ensure that adequate space is provided for each rubber plant so that there is good exposure to sunlight for development of the aerial portions and sufficient volume of soil for spread of the root system. In addition to the direct influence on growth and yield, the density of planting can affect the duration of immature period (Westgarth and Buttery, 1965). The thickness of the bark and rate of its renewal after commencement of tapping, and the incidence of panel diseases are also influenced by density of planting

(Napitupulu, 1977; Leong and Yoon, 1982; Webster, 1989). It is also reported that planting density determines the yield per tapper and the cost of tapping (Barlow and Lim, 1967).

The yield per ha may, up to certain limit, be higher when the density is high, but yield per tree will be high when the stand is less. When rubber prices are high or when family labour is employed for tapping, higher yield per ha resulting from higher density may be more profitable. On the other hand, when labour costs are high and rubber prices low, it is desirable to have higher yield per tree resulting from a lower stand per ha. Therefore, a compromise between the two is necessary to decide the density of planting and the final stand in an area.

The density of plants recommended is 420 to 445 plants per ha in the case of buddings or plants proposed to be field-budded and 445 to 520 plants per ha in the case of seedlings. Some common spacings adopted in the above cases are given in Table 2.

Table 2. Density of plants under different terrains and planting materials

Planting material and terrain	Spacing (m)	Stand/ha
Buddings: in hilly areas	6.7 x 3.4	445
in flat areas : square	4.9 x 4.9	420
triangular	4.9 x 4.9	470
Seedlings: in hilly areas	6.1 x 3.0	539
in flat areas : square	4.6 x 4.6	479

Seedlings show genetic variability and the poor ones may have to be removed progressively. A higher initial stand is recommended for allowing proper thinning out. Table 3 gives the number of trees per ha at different spacings in square and rectangular planting systems.

3.2 Lining

The procedure for lining depends on the planting system and spacing to be adopted. Rubber can be planted adopting square, rectangular, triangular (equilateral triangle or quincunx system), avenue or hedge planting system (Edgar, 1958). Of these, the triangular and square systems offer well-balanced growth of the crown and root system. However, these systems are suitable only for level or near level lands. The rectangular system can be adopted in level areas and slopes. In this system, trees along the rows become closer and rows wide apart as in avenue planting. Because of this, the distance to be walked for tapping becomes shorter. The shading of the inter-rows is delayed and consequently the ground covers persist longer. However, avenue planting is more susceptible to wind damage because of the widely exposed inter-rows. Hedge planting is an extreme type of avenue planting in which the rows are so far apart that the branches of trees do not meet overhead to form a closed canopy. The wider rows increase the risk of wind damage and the growth is less uniform than in avenue planting. The absence of shade increases the danger of invasion of the inter-rows by noxious weeds. Hedge planting is not commonly practised now and it is advantageous only when intercropping is attempted.

Table 3. Number of trees per ha at different spacing* (square or rectangular)

cm (ft)	180 (6)	200 (7)	240 (8)	270 (9)	300 (10)	340 (11)	370 (12)	400 (13)	430 (14)	460 (15)	490 (16)	520 (17)	550 (18)	580 (19)	610 (20)	640 (21)	670 (22)	700 (23)	730 (24)	760 (25)
180 (6)	2990	2562	2244	1994	1794	1631	1495	1379	1282	1196	1122	1055	996	944	897	862	815	781	749	717
200 (7)		2197	1922	1707	1537	1399	1282	1184	1097	1025	961	904	855	810	768	731	699	670	633	615
240 (8)			1683	1495	1347	1223	1122	1035	961	897	840	791	749	709	672	640	613	586	561	539
270 (9)				1329	1196	1087	996	919	855	798	749	702	665	630	598	568	544	519	499	479
300 (10)					1077	979	897	828	768	717	672	633	598	566	539	511	489	467	450	425
340 (11)						890	815	754	699	652	613	576	544	514	489	467	445	425	403	390
370 (12)							749	689	633	598	561	529	499	472	450	427	408	390	376	358
400 (13)								638	591	551	516	487	460	442	415	395	376	361	346	331
430 (14)									549	511	479	452	427	405	385	366	348	334	321	309
460 (15)										479	450	423	398	378	358	341	326	311	299	293
490 (16)											420	395	376	353	336	321	306	292	279	269
520 (17)												373	351	334	316	301	287	274	264	252
550 (18)													331	314	299	284	272	259	250	240
580 (19)														299	284	269	257	247	237	227
610 (20)															269	257	245	235	225	215
640 (21)																245	232	222	213	205
670 (22)																	222	213	203	195
700 (23)																		203	195	188
730 (24)																			188	180
760 (25)																				173
790 (26)	689	591	516	460	415	400														
850 (28)	640	549	479	427	385															
910 (30)	598	511	447	398	358															
970 (32)	561	479	427	385																
1030 (34)	529	452	395																	
1090 (36)	499	427	373																	
1150 (38)	472	405																		
1210 (40)	447	385																		

* Spacing (ft) has been converted to the nearest 10 cm

The figures in the brackets are the corresponding space in ft

3.2.1 Rectangular or square planting

For rectangular planting, the lines should be oriented east to west to intercept maximum sunlight. A compass, a number of marking pegs and two ropes are required for lining (Edgar, 1958). One of the ropes can be used for the base line and the other for the guide lines. The planting distances are marked with coloured rags on the ropes.

As the initial step, a base line is fixed in the cleared area. The longest straight boundary running north to south would be the most convenient base line. One guide peg is fixed at the beginning of the proposed base line at one end, say, the southern end, and the compass kept over this guide peg No. 1 (corner peg).

A shot is taken due north and the guide peg No. 2 fixed at the extreme end of the lining rope. The planting points are then pegged at the marks along this base line using smaller pegs. Again, with the compass over the corner peg, another shot is taken east or west, depending on the shape of the land, and another guide peg and smaller pegs are fixed. The process is repeated at the other end where guide peg No. 2 has been fixed. In this way,




Fig. 1. Lining for rectangular or square planting

the three sides of the square or rectangle are formed. Advances are made from the base to the open end of the square or rectangle with the lining rope held (north – south) at each peg on the guide lines and pegging done along the ropes at the rag marks (Fig. 1).

3.2.2 Quincunx or equilateral - triangle planting

The system is also known by the names quincunical or triangular planting system. Here also, the base line is aligned in the same way as in the case of square planting. The guide lines are put by diagonal lining at an angle of 60 or 120° to the base line. The plant points are marked along the guide lines at the required spacing which is marked on the rope. The distances between any two plant points of a set of three adjacent points which constitute an equilateral triangle, are equal. In this system the spacing can be expressed by single number e.g. 4.9 or 5 m. An alternate method for lining in this system is to first align the guide lines at a spacing equal to 86.6 per cent of the required spacing. For example, if 5 m is the required spacing, the guide lines may be aligned at a spacing of 4.33 m. An extra half planting distance may be marked beyond the last tree point on the rope. In the second and subsequent alternate rows, this marker is brought against the guide peg, and smaller pegs are placed in the normal way against the coloured rags on the ropes (Fig. 2). The guide pegs in these alternate rows are removed after the lining is completed. The spacing along each row which is marked on the rope should be the actual planting distance viz. 5 m in the case of the example cited above. By adopting this system of planting, about 15 per cent more plants can be accommodated in a given area compared to the square system for the same spacing.




Fig. 2. Lining for quincunx system planting

3.2.3 Contour planting

This system is suited for undulating and hilly lands where the slope is generally more than eight per cent. Here the planting points are marked as lines passing through points of the same elevation. A guide line is selected down the hill along an average slope of the clearing. Guide pegs are driven in along this guide line to mark the contour intervals. For this, the horizontal interval is measured by holding the tape level. Once the guide lines are aligned and marked, it is possible to commence marking of the planting points using a road tracer or other suitable instrument for levelling. Contour lines are aligned right and left of the guide lines with pegs to indicate planting points. The degree of slope varies from place to place in a field and because of this reason the distances between contours also vary. When gradient increases, contours converge, and when the slope is less, they widen. If the distance between contour lines does not vary greatly, it is possible to maintain a fairly uniform planting density by varying the spacing between the planting points in the rows. When this is not practicable, it is necessary to stop a contour line where the adjacent contours come too close, and to start additional contours when the rows become too wide. A rule of thumb is that when the distance between terraces is reduced to two-thirds of the normal distance, alternate terraces are stopped, and where it exceeds one and one third of the normal, additional terraces are introduced.




Fig. 3. Levelling triangle and trapezium

When the area to be lined is smaller, a useful instrument would be triangular or rhomboid wooden frame with the points of its legs at the required planting distance (Fig. 3) and fixed with a spirit level or plumb line to ensure the correct level. The levelling triangle is placed with one leg against the guide peg and when the instrument is correctly levelled, a peg is driven in where the second leg meets the ground. Subsequent points are marked using the preceding point as the guide, taking care to alternate the legs of the frame to minimize any possible error.

3.3 Pitting and refilling

In order to provide favourable conditions for the early establishment and growth of the young plant, a pit is dug at the planting point and refilled with fertile topsoil. The standard size of the pit is 75 cm³. The size of pits can vary depending upon the type of planting material used and the nature of the soil. Stumped buddings need wider and deeper pits, while smaller pits are sufficient for small and medium-sized polybag plants. Larger pits are advantageous on hard, compact or stony soils. The cost of digging very large pits cannot be justified unless there is definite advantage for root development. The main consideration is that the pit should be big enough to accommodate the root system of the plant. On economic consideration, in deep, loose and friable soils, the pits are sometimes dug wider at the top and tapering towards the bottom, or the depth reduced to about 60 cm with a central crowbar ('alavang') hole of 15 cm or more depth for the tap root.

Pitting can be initiated as soon as the work of clearing and lining has sufficiently progressed (Plate 17. a). While digging the pit, the topsoil may be deposited on one side and the subsoil on the other (Plate 17. b). It is important to complete the refilling operation before the onset of the monsoon and well ahead of planting so that there is sufficient time left for the soil to settle. Filling should be done using fertile topsoil as far as possible. Apart from the topsoil obtained while digging a pit, sufficient surface soil has to be collected from the surroundings, stones and roots removed and used for filling. When organic and phosphate manures are to be applied to the pits, they are thoroughly mixed with the top 20 cm soil in the pit. The pit should be filled to about 5 cm above ground level. A peg may be fixed at the centre of the pit to locate the position at the time of planting (Plate 17. c). When large rubber areas are replanted, lining and pitting operations are sometimes undertaken before felling the trees during September to December period previous to the year of planting in order to minimize the rush of operations during the planting season (Plate 17. d).

3.4 Soil conservation

Cutting of terraces along contours is a recommended practice on hilly and undulating lands for conserving moisture and preventing soil erosion. Construction of continuous terraces along planting rows, though initially expensive, provides the best method of protection against the risk of erosion. Moreover, the terraces serve as footpath and help to conduct many operations along the rows, such as weeding, pruning, tapping, collection and inspection in a cheap, easy and effective manner.

For making contour terraces, the soil on the hillside is cut from a distance of about 60 to 75 cm in front of the planting row and thrown back, so that the terrace thus formed will have a width of 1.25 to 1.50 m and an inward drop of 20 to 30 cm. The angle of the slope to the back of the terrace should depend on the type of soil and intensity of rainfall. For example, steeper slope is necessary in light soil than in clay or gravelly soil. Similarly, the slope should increase with increasing intensity of rainfall. The soil, cut and removed, is used to extend the front of the terrace and sometimes also to provide a small bund on the outer edge. Narrow blocks of uncut earth protruding from the backwall at intervals of 10 to 20 m should be left along the terrace to check lateral flow of excess rain water along the terrace. In order to reduce expenses during the year of planting, planting on hillsides can also be done on square platforms of size about 1.25 x 1.25 m (honeycomb terrace). These individual tree platforms are joined together later to make complete and continuous terraces. Alternatively these platforms can be connected with narrow outer edges of about 60 cm width to facilitate easy movement of workers and staff.

In order to further reduce soil erosion, silt pits are taken and maintained in steep areas. Trenches of about 120 cm length, 45 cm width and 60 cm depth are taken along the contours at suitable intervals depending on the degree of slope. More pits are advisable when the slope is more. About 100 to 200 pits are desirable for a hectare of plantation. They are aligned in between the planting lines or contour terraces in such a way that the pits in adjacent inter-rows are in a staggered manner. The soil from the pits should be thrown below the pit to form small earth bunds. The water and soil particles washed off from above are partly collected in these pits. The silt deposited in the pits is periodically removed and placed on the lower side of the pit.

Construction of level contour terraces with stone-pitched retaining walls ('edakayyala') is another effective method of soil and water conservation. The washed off soil is deposited on the upper sides of the terraces while water filters through the terraces. The distance between terraces depends on the degree of slope. The contour terraces, 'edakayyalas', etc. should be periodically repaired.

3.5 Drainage

Drainage is important on flat land or gentle slopes with a permanent or seasonal high water table. Adequate drainage enhances soil aeration and stimulate beneficial microbial activity and proper establishment of ground covers leading to improved growth of rubber. Proper drainage also enhances good root development and consequent better absorption of water and nutrients. The drainage systems designed should keep the water table 1.0 to 1.5 m below the soil surface. The natural waterways available in the area may be cleared, dressed or deepened to form a satisfactory drainage system. If such outlet drains do not exist, proper drainage has to be provided. Depending on the drainage requirement, main drains are dug at intervals of 100 to 200 m and lead to an outlet drain. If necessary, side drains or contour drains at required intervals are dug subsequently such that they meet the outlet drains at right angles. The drainage system once constructed should be desilted and repaired periodically.

3.6 Materials for planting

Different kinds of planting materials are used for establishment of rubber plantations. The important ones among them are seeds, seedling stumps, budded stumps and advanced planting materials comprising of stumped buddings, polybag plants and soil core plants.

3.6.1 Seeds and seedling stumps

Seeds can be used either for seed at stake planting or for preparing seedling stumps. For raising seedling stumps only polyclonal seeds are recommended.

3.6.2 Budded stumps

Budded stump is a very convenient form of planting material. It can easily be transported and planted with much less effort compared to polybag plants. Green-budded stumps are mostly used for raising polybag plants.

3.6.3 Advanced planting materials

With the object of shortening the period of unproductive phase in the field, advanced planting materials are now being used. Maintenance in the field is more expensive than in the nursery. Therefore, new techniques have been developed for growing the planting materials in nurseries for longer periods and transplanting them to the field without disturbing the root system. Stumped buddings, stumped three part plants, polybag plants, soil core plants and core stumps are the different types. Advanced planting materials are also useful for gap filling during subsequent years.

3.6.3.1 Stumped buddings

These materials are already grown for one to two years in the nursery and are expected to come to tapping in a shorter period after planting. The cost of raising stumped buddings is less than that of polybag plants. However, in India, the use of stumped buddings on commercial scale is not popular because of the difficulty in their maintenance during the long dry period.

3.6.3.2 Polybag plants

Polybag plants (Plate 17. e) are definitely advantageous for easy establishment and for shortening the immaturity period (Marattukalam and Nair, 1982). This method is useful for reducing vacancies to the minimum. This will also lead to uniform growth of the stand. The initial cost is high and careful handling is necessary.

3.6.3.3 Soil core plants

Transplanting at the three whorl stage with an intact core of soil holding the root system is most ideal. The success depends on the clayey nature of the soil. Handling the soil core is also difficult.

3.6.3.4 Core stumps

Core stumps combine the advantages of polybag plants and budded stumps. The problem faced by stumped buddings is also not experienced here.

3.6.4 Seedlings vs. clones

Both seedlings and buddings have merits and demerits. Seedlings are generally more vigorous and hence attain tappareability earlier than buddings, show greater tolerance

to adverse soil and climatic conditions and hence are more easy to establish and maintain. Seedlings generally possess thicker bark and hence are easier to tap. Owing to the genetic diversity, the damages caused by disease and unfavourable climatic factors are only partial or generally less in seedling populations. Because of the vigorous growth, seedlings give higher timber yield. However, seedling populations have certain serious defects such as high susceptibility to brown bast (TPD) and tolerance to only low intensities of tapping. They also exhibit high variation in growth, vigour and yield and this necessitates initial higher stand and subsequent thinning out which cause wastage. Variations in thickness of bark and properties of latex also cause many practical difficulties in tapping and processing. Seedling trees have tapering trunk and therefore initial opening for tapping has to be made at a lower level, resulting in formation of bark islands when subsequent panels are opened. On the other hand, clones are noted for their uniformity. Since there are different clones possessing different specific characters, selection of materials suited for specific purposes is possible. The production potential of many modern clones is substantially higher than that of seedlings. Under ideal agroecological conditions clones are considered better planting materials than seedlings. Seedlings are preferred only in areas where establishment of plants is difficult.

3.7 Planting

The success of planting depends on the prevailing weather conditions, quality of the planting materials used and the care with which the planting operation is done. It is very important that planting is always done during favourable weather. Periods of continuous heavy rains should be avoided, because the soil in the pits becomes slushy and this would lead to high rates of casualty. Continuous wet weather can be expected during June-July in the major rubber growing areas in India and hence this period is considered to be ideal for planting rubber. The actual method of planting will depend on the materials used for planting.

3.7.1 Seed at stake

Three or four germinated seeds are directly planted in the centre of the refilled pits in the field. After establishment of the seedlings, the weak plants are removed. The plant bases are always kept free of weeds. During the initial year, the seedlings are manured with NPK Mg 10:10:4:1.5 fertilizer mixture at the rate of 225 g per plant in a single dose, six weeks after planting the germinated seeds. Seedlings other than approved high yielding polyclonal ones are field-budded during April-May subsequent to planting when the plants attain the required size. If the conditions are not very favourable, plants may attain buddable size only during September-October. The field-budded plants are cut back *in situ* and the bud allowed to grow.

3.7.2 Seedling and budded stumps

Both seedling stumps and budded stumps should be planted in the main field as early as possible after pulling them out from the nursery. About 5 cm of the surface soil is first removed from an adequate area at the plant point to accommodate the lateral roots attached to the stump. Using a crowbar, a planting cavity is made to a depth equal to the length of the pruned tap root. The stump is then carefully inserted in the cavity

sufficiently deep in such a way that the lateral roots are properly accommodated in the area dug around the cavity for the purpose. Care should be taken to ensure that the tip of the root is in actual contact with the soil at the bottom of the cavity. The presence of air gap in the planting cavity results in failure of the stump. It is important to pack sufficient loose soil in the cavity around the tap root by pushing the crowbar into the edge of the planting hole as deep as the tap root, or more, in a slanting manner, and then pulling it towards the stump which is firmly held in position. This process is repeated from the other three sides of the stump.

Under favourable conditions, the bud usually sprouts in three to four weeks after planting. Sprouting may be delayed up to several months if the budded stock seedlings were left in the nurseries for periods longer than a month before they are cut back and transplanted as budded stumps. The delay is due to the overgrowth of callus. Too long a portion of the stock seedling above the bud patch also will cause delay in bud sprouting as well as formation of too many offshoots.

3.7.3 Stumped buddings

The planting holes are refilled and allowed to settle as in the case of planting budded stumps. Just before planting, a hole is dug 15 to 25 cm shallower than the length of tap root of the stumped budding to be planted. A smaller cavity is made in the centre of this hole using a crowbar to a further depth of 15 to 25 cm, depending upon the length of the tap root. The end of the tap root of the stumped budding is firmly wedged into this hole. The soil is filled into the planting hole and pressed firmly around the base of the plant to ensure firm anchorage. The plant base is thickly mulched.

The success of stumped budding depends much on the receipt of frequent and adequate rain after planting. A prolonged dry period immediately after planting will seriously affect the success of establishment. Under such conditions, watering at the rate of 10 to 15 L per plant, once in four to five days, is recommended. All shoots which develop towards the top of the stem are allowed to grow until the plant is well established. Subsequently, the number is reduced to three well-spaced shoots. If die-back is noticed soon after planting, the stem has to be cut back to healthy tissues and suitable wound dressing compounds applied. Mini stumps are planted more or less in the same way as budded stumps. However, pre-planting operations such as pollarding, root pruning and whitewashing are essential. Plant bases should be mulched immediately after planting.

3.7.4 Polybag plants

At the time of transplanting, the top whorl of leaves of the polybag plant should be fully mature. Just before removing the plant from polybag nursery, all the plants are watered well. The soil around the bag is removed and the bags are taken out of the trench. Dressing of the lateral roots and tap root, if grown out of the bags, may be necessary. Then they are carried to the planting points. A planting hole slightly bigger than the size of the bag is made. The bottom of the bag is completely cut and then the bag along with the plant is inserted into the planting hole. A vertical cut is made at the bottom of the plastic sleeve, taking care not to damage the roots. Then the cut is continued as the hole is gradually filled so that the cylinder of soil is unbroken. When the hole is